

# Pose estimation

**Note:** The environment has been set up. Simply follow the instructions to run the corresponding function commands to use it.

## 1. Pose Estimation: Image

Use yolo11n-pose.pt to predict the image provided with the Ultralytics project.

Go to the code folder:


```
cd /home/sunrise/ultralytics/ultralytics/yahboom_demo
```

Run the code:

```
python3 03.pose_image.py
```

### Preview

Yolo recognition output image location: /home/sunrise/ultralytics/ultralytics/output/



Sample code:

```
from ultralytics import YOLO
```

```

# Load a model
model = YOLO("/home/sunrise/ultralytics/ultralytics/yolo11n-pose.pt") #
pretrained yolo11n-pose model
# model = YOLO("/home/sunrise/ultralytics/ultralytics/yolo11n-pose.onnx")
# model = YOLO("/home/sunrise/ultralytics/ultralytics/yolo11n-pose_ncnn_model")

# Run batched inference on a list of images
results = model("/home/sunrise/ultralytics/ultralytics/assets/people.jpg") #
return a list of Results objects

# Process results list
for result in results:
    # boxes = result.boxes # Boxes object for bounding box outputs
    # masks = result.masks # Masks object for segmentation masks outputs
    keypoints = result.keypoints # Keypoints object for pose outputs
    # probs = result.probs # Probs object for classification outputs
    # obb = result.obb # Oriented boxes object for OBB outputs
    result.show() # display to screen

    result.save(filename="/home/sunrise/ultralytics/ultralytics/output/people_output.jpg") # save to disk

```

## 2. Instance Segmentation: Video

Use yolo11n-pose.pt to predict videos in the Ultralytics project (not included with Ultralytics).

Go to the code folder:


```
cd /home/sunrise/ultralytics/ultralytics/yahboom_demo
```

Run the code:

```
python3 03.pose_video.py
```

### Preview

Yolo recognition output video location: /home/sunrise/ultralytics/ultralytics/output/



Sample code:

```
import cv2
from ultralytics import YOLO

# Load the YOLO model
model = YOLO("/home/sunrise/ultralytics/ultralytics/yolo11n-pose.pt")
# model = YOLO("/home/sunrise/ultralytics/ultralytics/yolo11n-pose.onnx")
# model = YOLO("/home/sunrise/ultralytics/ultralytics/yolo11n-pose_ncnn_model")

# Open the video file
video_path = "/home/sunrise/ultralytics/ultralytics/videos/people.mp4"
cap = cv2.VideoCapture(video_path)

# Get the video frame size and frame rate
frame_width = int(cap.get(cv2.CAP_PROP_FRAME_WIDTH))
frame_height = int(cap.get(cv2.CAP_PROP_FRAME_HEIGHT))
fps = int(cap.get(cv2.CAP_PROP_FPS))

# Define the codec and create a Videowriter object to output the processed video
output_path =
"/home/sunrise/ultralytics/ultralytics/output/03.people_animals_output.mp4"
fourcc = cv2.VideoWriter_fourcc(*'mp4v') # You can use 'XVID' or 'mp4v'
depending on your platform
out = cv2.VideoWriter(output_path, fourcc, fps, (frame_width, frame_height))

# Loop through the video frames
while cap.isopen():
    # Read a frame from the video
    success, frame = cap.read()

    if success:
```

```

# Run YOLO inference on the frame
results = model(frame)

# Visualize the results on the frame
annotated_frame = results[0].plot()

# Write the annotated frame to the output video file
out.write(annotated_frame)

# Display the annotated frame
cv2.imshow("YOLO Inference", cv2.resize(annotated_frame, (640, 480)))

# Break the loop if 'q' is pressed
if cv2.waitKey(1) & 0xFF == ord("q"):
    break
else:
    # Break the loop if the end of the video is reached
    break

# Release the video capture and writer objects, and close the display window
cap.release()
out.release()
cv2.destroyAllWindows()

```

## 3. Pose Estimation: Real-Time Detection

### 3.1. Launching the Camera

Launch the following program based on your camera model. In the terminal, enter:

```

#usb camera
ros2 launch usb_cam camera.launch.py
#nuwa camera
ros2 launch ascamera hp60c.launch.py

```

Open another terminal and navigate to the code folder:

```
cd /home/sunrise/ultralytics/ultralytics/yahboom_demo
```

Run the code: Click the preview screen and press q to terminate the program!

```
python3 03.pose_camera_usb.py
```

### Preview

Yolo recognition output video location: /home/sunrise/ultralytics/ultralytics/output/





Sample code:

```

#!/usr/bin/env python3
import rclpy
from rclpy.node import Node
from sensor_msgs.msg import Image, CompressedImage
from cv_bridge import CvBridge
import cv2
from ultralytics import YOLO
import os

class Image_detection(Node):
    def __init__(self):
        super().__init__('Image_detection')
        self.model = YOLO("/home/sunrise/ultralytics/ultralytics/yolo11n-pose.onnx")
        self.camera_type = os.getenv('CAMERA_TYPE', 'usb')
        self.bridge = CvBridge()
        if self.camera_type == 'usb':
            topic_name = '/usb_cam/image_raw'
        else:
            topic_name = '/ascamera_hp60c/camera_publisher/rgb0/image'

        self.subscription = self.create_subscription(Image, topic_name,
            self.image_callback, 10)

        # Get the video frame size and frame rate
        frame_width = 640
        frame_height = 480
        fps = 15
        output_path =
"/home/sunrise/ultralytics/ultralytics/output/03.pose_camera_usb.mp4"

```

```

fourcc = cv2.VideoWriter_fourcc(*'mp4v') # You can use 'XVID' or 'mp4v'
depending on your platform
self.out = cv2.VideoWriter(output_path, fourcc, fps, (frame_width,
frame_height))

def image_callback(self, msg):
    cv_image = self.bridge.imgmsg_to_cv2(msg, desired_encoding='bgr8')

    self.proecc(cv_image)

# Loop through the video frames
def proecc(self, frame):
    # Run YOLO inference on the frame
    results = self.model(frame)

    # Visualize the results on the frame
    annotated_frame = results[0].plot()

    # Write the annotated frame to the output video file
    self.out.write(annotated_frame)

    # Display the annotated frame
    cv2.imshow("YOLO Inference", cv2.resize(annotated_frame, (640, 480)))

    # Break the loop if 'q' is pressed
    cv2.waitKey(1) & 0xFF == ord("q")

def cancel(self):
    cv2.destroyAllWindows()
    self.out.release()

def main(args=None):
    rclpy.init(args=args)
    node = Image_detection()
    try:
        rclpy.spin(node)
    except KeyboardInterrupt:
        pass
    finally:
        node.cancel()
        node.destroy_node()
        rclpy.shutdown()

if __name__ == '__main__':
    main()

```